

Seetrol DESK

한국어 ▾

Seetrol Call 원격제어

원격제어에 동의하시면 상대방이 알려준 5자리 숫자를 입력하고 Enter를 클릭하여 프로그램을 다운받아 실행하세요.

상대방이 알려준 5자리 번호를 입력하세요


ENTER

SeetrolDesk Seetrol Uninstaller 사용 방법


원격 상대방이 인터넷을 통해 고객님의 PC에 접속하여 화면을 보면서 키보드와 마우스를 제어합니다.

586.co.kr 페이지에 접속하신 후
페이지 하단의 **SeetrolDesk**를
클릭하여 상담원용 프로그램을
실행하고 설치하십시오.

Seetrol DESK 사용법 - 상담원 프로그램 로그인




The screenshot shows the Seetrol Desk login interface. At the top, there is a red header with the text 'Seetrol Desk' and a user icon. Below the header, there is a large empty rectangular area on the left. On the right, there is a login form with two input fields: 'View ID' and 'Password', both highlighted with a green border. Below these fields is a '로그인' (Login) button. At the bottom of the screen, there is a search bar with the text 'Search' and a '접속' (Connect) button. Below the search bar, there is a table with the following columns: 'Session', 'Login Type', 'StandBy', 'Desk ID', and 'Group'. The table is currently empty. At the bottom left, the URL 'https://www.seetrol.co.kr' is displayed, and at the bottom right, the version number 'v24.3.15.1' is shown.



The screenshot shows the Seetrol Desk interface after a successful login. The top header remains the same. Below the header, there is a log history window on the left with the following entries:
10:05:48 | Recv. Server Info. : cont2.586.kr
10:05:48 | Try Connecting to Server
10:05:48 | Connected to Seetrol
10:05:48 | Recv. Session Code : 8711
10:05:48 | Expiry Date : 2024-05-17
On the right, there is a user profile section with a green box around the text 'Super Desk No : 18820'. Below this, the user name 'hysj93' is displayed, followed by a password field with 10 dots. At the bottom right, there is a '로그아웃' (Logout) button. The search bar and '접속' button are still present. The table at the bottom is empty. The URL 'https://www.seetrol.co.kr' and version 'v24.3.15.1' are at the bottom.

Seetrol WITH의 manager 프로그램에서 사용하는 ID와 PW를 그대로
사용하실 수 있습니다



Seetrol DESK 한국어

Seetrol Call 원격제어

원격제어에 동의하시면 상대방이 알려준 5자리 숫자를 입력하고 Enter를 클릭하여 프로그램을 다운받아 실행하세요.

18820 ENTER

SeetrolDesk Seetrol Uninstaller 사용 방법

원격 상대방이 인터넷을 통해 고객님의 PC에 접속하여 화면을 보면서 키보드와 마우스를 제어합니다.

원격지원요청자에게 DeskNo를 알려줍니다. 그림 예에서는 18820이라는 5자리 숫자를 알려주어 원격요청자가 입력하게 한 후 ENTER를 클릭하면 18820.Exe 라는 파일을 내려 받을 수 있습니다.

Seetrol DESK

다운로드가 완료되었습니다

18820.exe 파일이 다운로드 되었습니다.
파일을 실행하신 후 아래 그림처럼 보여지는 4자리 숫자를 상대방에게 알려주세요

Seetrol Call

로그아웃

원격 상대방이 인터넷을 통해 고객님의 PC에 접속하여 화면을 보면서 키보드와 마우스를 제어합니다.

Download 폴더에 저장된 18820.exe 파일을 실행합니다. 실행하면 4자리의 임의의 숫자가 생성됩니다.



The image shows the "Seetrol Desk" interface. At the top, there is a red header with the title "Seetrol Desk" and user information "Super Desk No : 18820" and "hysj93". Below the header is a log of connection events:

- 10:05:48 | Recv. Server Info. : cont2.586.kr
- 10:05:48 | Try Connecting to Server
- 10:05:48 | Connected to Seetrol
- 10:05:48 | Recv. Session Code : 8711
- 10:05:48 | Expiry Date : 2024-05-17

Below the log is a search bar and a "로그아웃" (Logout) button. At the bottom, there is a table of active sessions:

Session	Login Type	StandBy	Desk ID	Group	Public IP
1	2040	Normal		0	106.249.236.20

A green box highlights the first row of the table. Below the table, there is a text instruction: "해당 2040 세션을 더블클릭하여 원격지 PC를 제어 시작" (Double-click the corresponding 2040 session to start remote control of the PC). The URL "https://www.seetrol.co.kr" and version "v24.3.15.1" are visible at the bottom.